



Turbonomic 7.21.4 Installation Guide

Turbonomic, Inc

500 Boylston St, 7th floor
Boston, MA 02116 USA
Phone: (844) 438-8872
www.turbonomic.com

COPYRIGHT

Copyright © 2010 - 2020 Turbonomic, Inc. All rights reserved

END-USER LICENSE AGREEMENT

https://cdn.turbonomic.com/wp-content/uploads/Turbonomic_Click_Through_Customer-License.pdf

Contents

Introduction.....	4
Minimum Requirements.....	5
Installing on VMware Systems.....	7
General Configuration Tasks.....	14
(Required) Synchronizing Time.....	14
(Optional) Enforcing Secure Access.....	16
License Installation and First-time Login.....	18
Single Sign-On Authentication.....	19
Example of IdP Metadata.....	22
Disabling Single Sign-On.....	23
Support for Single Logout.....	24
Updating Turbonomic to a New Version.....	25
Appendix A: Turbonomic Components.....	29
Appendix B: What Are the Typical Settings for an IdP?.....	31



Introduction

Thank you for choosing Turbonomic, the Intelligent Workload Automation Management solution for Virtualized Environments. This guide gives you information you need to install Turbonomic in your virtual environment, install your license, and get started managing your resources.

If you have any questions, please contact Turbonomic support. Visit our support site at <https://support.turbonomic.com>.

Sincerely:

The Turbonomic Team



Minimum Requirements

The requirements for running a Turbonomic instance depend on the size of the environment you are managing. Turbonomic keeps a real-time representation of your environment in memory. The greater the number of entities to manage, and the greater the relationships between them, the more resources you need for the VM that runs Turbonomic. And as the VM requirements increase, so do the requirements for the physical machine that hosts the VM.

The requirements listed here are recommendations that you should keep in mind as you plan your Turbonomic deployment. After deploying, if you find that you need to change memory capacity, CPU capacity, or both for the VM, you can shut it down, make changes, and then power it up again to use the new capacity.

NOTE:

The machine that hosts the Turbonomic platform must support the SSE4.2 instruction set. Support for this instruction set was introduced at different times for different chip manufacturers:

- Intel: November 2008
- AMD: October 2011

The machine you use to host Turbonomic should be newer than these dates. On a Linux system, you can run the following command to check for this support:

```
cat /proc/cpuinfo | grep sse4.
```

For more information, see the glossary entry at <http://www.cpu-world.com/Glossary/S/SSE4.html>.

In most cases you can run Turbonomic on a host that meets the following minimum requirements:

Supported Hypervisors		Storage Requirements	Memory	CPUs
VMware	vCenter versions 5.5, 6.0, 6.5, and 6.7	1.25 TB or greater. NOTE: Can be thin provisioned depending on the storage requirements.	128 GB NOTE: For 10,000 VMs or less, 64 GB can work.	8 vCPUs

Turbonomic provides an OVA file which is preconfigured with two hard drives. A minimum of 1.25 TB is necessary to ensure that the drives have the proper amount of space for storage.

Turbonomic requires a browser capable of displaying HTML5 pages.

Turbonomic requires static IP addressing.



Installing on VMware Systems

This download of the Turbonomic instance is in the .OVA 1.0 format.

To install Turbonomic:

1. Download the Turbonomic installation package.

The email you received from Turbonomic includes links to the Turbonomic download pages. You can get the installation package from there.

The installation package includes the `turbonomic_t8c-<version>-<XXXXXXXXXXXXXXXX>.ova` file where `<version>` is the Turbonomic version number and `<XXXXXXXXXXXXXXXX>` is the timestamp.

For example: `turbonomic-t8c-7.17.3-20190916164429000.ova`

The OVA file deploys as a VM with the Turbonomic components already installed.

2. Import the OVA file into your datacenter.

Use the vCenter Server client to import the OVA into your environment.

3. Deploy the Turbonomic VM.

Create the VM using the OVA file. Ensure that the physical machine hosting the VM meets the minimum requirements (see [Minimum Requirements \(on page 5\)](#)).

Manually modify the default values for CPU and Memory:

- a. Right-click the VM and choose **Edit Settings**.
 - b. Type **8** for CPU.
 - c. Type **64** for Memory.
 - d. Click **OK** to save the settings
 - e. Power on the VM.
4. Open the remote console.

For the Turbonomic VM that you just deployed:

- a. Choose the **Summary** tab.
- b. Click **Launch Remote Console**.

5. Set up the Turbonomic System Administrator account.

- a. In the remote console, log in with the following default credentials:

- Username: `turbo`

Do not use the account name, `root`.

- Password: `vmturbo`

Then, you will be prompted to enter a new password.

- b. Enter your new password.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

NOTE:

Be sure to save the turbo account credentials in a safe place. For security reasons, this is the only account that can access and configure the Turbonomic VM.

- c. Enter your new password again to verify it.

6. Update the root password.

The platform uses the `root` account for certain processes, such as rolling up log messages in `/var/log/messages`. To ensure the account credentials are current, you must change the password:

- a. Open a SuperUser session.

- In the remote console, enter `su -`
- At the password prompt, enter `vmturbo`

- b. Reset a new password.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

NOTE:

Be sure to save the root account credentials in a safe place.

- Enter the command, `passwd`
- At the new password prompt, enter the new password
- At the Retype prompt, enter the password again

You should see the message `password updated successfully`.

- c. Exit the SuperUser session.

Enter `exit`.

7. Set up the static IP address.

- a. In the remote console, start the NetworkManager user interface.

Type: `sudo nmtui`

- b. Edit the `eth0` ethernet connection.

Use the arrow keys to navigate in NetworkManager.

In NetworkManager, choose the `Edit` option and click `<OK>` to open the Edit Connection dialog box.

Then, choose `Ethernet` from the list of options and fill out the following information (values given are examples only).

- Profile Name: `System eth0`
- Device: `eth0`

Next, expand `IPv4 CONFIGURATION` and fill out the configuration subsettings based on your environment:

- IPv4 Configuration: `<Manual>`
- Addresses: Specify the static IP address you want, with the subnet mask on the same line. For example:
`10.0.254.10/24`
- Gateway, DNS Servers, and Search domains: Give values that are valid for your network environment.

When you are satisfied with your settings, click `<OK>` and `<Back>` to return to the configuration list. Verify that the connection you just created is present.

- c. Make a note of the IP address that you just specified.
- d. Exit `NetworkManager`.

Click `<Quit>` to return to the command line.

8. Restart the network service in the Turbonomic VM.

Type: `sudo systemctl restart network`

9. Optional: Set up a proxy for internet access.

To use a proxy for internet access, you should set it up before you install the Kubernetes nodes for the Turbonomic platform.

IMPORTANT:

Do not configure your proxy in the `/etc/environment` file. This configuration is for the host machine, and will interfere with Kubernetes networking. Instead, you must configure a proxy for the Kubernetes environment. The following instructions are to set up the installation process so it will configure your proxy upon install.

To verify that a proxy has not been configured for the host machine, open `/etc/environment`. The file should have no content. If a proxy has been configured in this file, delete the configuration statements and save your changes. Then log out of the host machine and log in again.

To set up a proxy for this installation:

- a. Note the IP address of your host machine.

When you set the static IP for this machine, you should have made a note of the IP address. If you do not know the machine's IP address, execute the following command:

```
ifconfig eth0
```

- b. Edit the Kubernetes setup so that `packagemanager` and `docker daemon` will use your proxy correctly.

Open the following file for edit:

```
/opt/kubespray/inventory/sample/group_vars/all/all.yml
```

- c. Specify the proxy to use.

Search for `http_proxy`. You should see the following two lines, commented out:

```
# http_proxy:
# https_proxy:
```

Uncomment the line for the protocol your proxy uses, and add the the proxy address and port. The most common protocol is HTTP, so you would uncomment `http_proxy` and specify your proxy server. For example:

```
http_proxy: "10.10.12.34:3123"
```

- d. Exclude this host VM from going through the proxy server.

Proxy configuration is to set up the Turbonomic components to go through the proxy. However, you should exclude the host machine.

In the same `/opt/kubespray/inventory/sample/group_vars/all/all.yml` file, search for `no_proxy`. Uncomment this line and specify the host VM. Use the IP address that you specified when you set a static IP. The line should read:

```
no_proxy: "<YourStaticIP>, node1, 127.0.0.1, 127.0.0.0"
```

Where `<YourStaticIP>` is the IP address you specified for the Turbonomic VM.

- e. Save your changes.

When you are done, save and close the file. This sets up the installation process to configure the proxy for the Turbonomic components.

- f. Update your `yum` configuration to use the proxy.

If you set up a proxy for your Turbonomic platform, then you should also set the same proxy for `yum`, so you can properly download and install component upgrades.

Open the file, `/etc/yum.conf` and search for `# proxy=`. Uncomment the line and add your proxy server IP and port. For example, the line should be similar to:

```
proxy=10.10.12.34:3123.
```

When you are done, save and close the file.

To verify that your proxy has been set, after you run the installation you can view the configuration in `/etc/systemd/system/docker.service.d/http-proxy.conf`. Find the `[Service]` section. It should contain your `proxy` and `no_proxy` settings. For example, it should be similar to:

```
Environment="HTTP_PROXY=http://10.10.12.34:3123" "NO_PROXY=<YourStaicIP>, node1, 127.0.0.1, 127.0.0.0"
```

If you want to change the proxy configuration after you have installed Turbonomic, please contact Technical Support.

10. Optionally, set the installation to the smaller memory requirement of 64 GB.

For minimum requirements, we recommend 128 GB of memory for the VM that hosts Turbonomic. However, if you plan to manage a smaller environment (10,000 VMs or less), you can install on a VM that provides 64 GB of memory. (See [Minimum Requirements \(on page 5\)](#)).

To set the smaller installation, you will set a symbolic link to the `charts_v1alpha1_xl_cr.yaml` file that you want to use:

- In a shell, `cd` to the `deploy/crds` directory:

```
cd /opt/turbonomic/kubernetes/operator/deploy/crds
```

- Remove the default symbolic link.

By default, the sumbolic link points the the 128 GB installation script. Use the command:

```
rm charts_v1alpha1_xl_cr.yaml
```

- Create a symbolic link to the 64 GB installation script:

```
ln -s charts_v1alpha1_xl_cr-64gb.yaml charts_v1alpha1_xl_cr.yaml
```

11. Deploy Turbonomic Kubernetes nodes.

When you deploy Turbonomic on Kubernetes, you deploy one Kubernetes node as a VM that will host pods to run the Turbonomic components. The script to deploy and initialize the Kubernetes node also deploys the Kubernetes pods that make up the Turbonomic application.

Start a secure session (SSH) on your Turbonomic VM as the turbo user and perform the following steps:

- Initialize the Kubernetes node and deploy the pods.

Execute the script: `/opt/local/bin/t8c.sh`

Do not specify `sudo` when you execute this script.

The script should take up to 20 minutes to complete.

- Verify that the the deployment succeeded.

At the end of the script output, in the summary section, verify that no errors are reported. If any errors are reported, contact Turbonomic Support.

- Verify that the Turbonomic application installed correctly.

To verify the installation of the application, execute the command:

```
kubectl get pods -n turbonomic
```

After all of the pods start up, the `READY` column should read `1/1` and the `STATUS` column should read `Running`.

You should see output similar to the following:

NAME	READY	STATUS	RESTARTS
action-orchestrator-b6454c9c8-mfl85	1/1	Running	0
api-7887c66f4b-shndq	1/1	Running	0
arangodb-7f646fc5fc-zhchw	1/1	Running	0
auth-5b86976bc8-vxwz4	1/1	Running	0
clustermgr-85548678d9-r5wb8	1/1	Running	0
consul-7f684d8cb8-6r677	1/1	Running	0
cost-5f46dd66c4-6d6cb	1/1	Running	0
group-5bfdfbc6f8-96bsp	1/1	Running	0
history-5fc7fbc855-6zslq	1/1	Running	0
kafka-74cc77db94-dfrbl	1/1	Running	0
market-5f54699447-z4wkm	1/1	Running	0
mediation-actionscript-57b4fc6df-4lzfz	1/1	Running	0
mediation-appdynamics-6d65f8766f-kb441	1/1	Running	0
mediation-hpe3par-d7c475c4c-v8ftc	1/1	Running	0
mediation-hyperp-6bd8c94df5-4dbzx	1/1	Running	0
mediation-netapp-7f8fc955d9-4kkdl	1/1	Running	0
mediation-oneview-7dbd7b54cf-7rfqp	1/1	Running	0
mediation-pure-58c4bd8cd9-8n256	1/1	Running	0
mediation-ucs-6f4bb9889-9rnqk	1/1	Running	0
mediation-vcenter-5bc4f5fbd4-nzm4j	1/1	Running	0
mediation-vcenterbrowsing-5c5987f66c-bfjq4	1/1	Running	0
mediation-vmx-6c59969b89-28t9j	1/1	Running	0
mediation-vmv-9c4878cf9-rfxnl	1/1	Running	0
nginx-5b775f498-sm2mm	1/1	Running	0

```

plan-orchestrator-6dffc4c9b6-p5t5n      1/1      Running  0
reporting-b44fbdfb4-8fjv5                1/1      Running  0
repository-6d555bb4bf-fxldh              1/1      Running  0
rsyslog-fd694878c-5tb2c                  1/1      Running  0
t8c-operator-558bcc758d-5h8mp            1/1      Running  0
topology-processor-b646b786b-9skp7       1/1      Running  0
zookeeper-5f65b5bf69-nnmbt               1/1      Running  0

```

d. Synchronize the system clock.

To ensure correct display of data, and to support Single Sign-On (SSO) authentication, you need to synchronize the system clock.

For information, see [Synchronizing Time \(on page 14\)](#) and [Single Sign-On Authentication \(on page 19\)](#).

e. Verify that the Load Balancer has installed correctly.

To verify the presence of the Load Balancer, execute the command:

```
kubectl get services -n turbonomic | grep LoadBalancer
```

You should see output similar to the following:

```
nginx LoadBalancer 10.10.10.10 10.10.10.11 443:32669/TCP,80:32716/TCP 17h
```

f. Enable mediation.

The t8c.sh script automatically enables mediation. No user action is required.

For Turbonomic to manage your IT environment, it must attach to targets in your environment so it can perform discovery and execute actions. The combination of the processes of discovery and action execution is *mediation*. This release of Turbonomic on Kubernetes supports mediation through the following targets. If you need to use additional targets that are not in this list, contact Turbonomic Support.

- Hypervisors
 - VMware vCenter 5.1, 5.5, 6.0, 6.5, and 6.7
 - Microsoft Hyper-V 2008 R2, Hyper-V 2012, and Hyper-V 2012 R2
- Cloud Managers
 - Amazon AWS
 - Microsoft Azure
 - Microsoft Enterprise Agreement
 - Microsoft System Center 2012 Virtual Machine Manager and System Center 2012 R2 Virtual Machine Manager
- Storage Managers
 - Pure Storage F-series and M-series arrays
 - NetApp Cmode/7mode using ONTAP 8.0+ (excluding AFF and SolidFire)
 - EMC VMAX using SMI-S 8.1+
 - EMC ScaleIO 2.x and 3.x
 - HPE 3PAR InForm OS 3.2.2+, 3PAR SMI-S, 3PAR WSAPI
- Fabric Managers
 - Cisco UCS Manager 3.1+
 - HPE OneView 3.00.04+

- Guest OS Processes
 - AppDynamics 4.1+
 - AppDynamics and Kubernetes
 - DynaTrace 1.1+
 - DynaTrace and Kubernetes
 - SNMP
- WMI Probe Supported Systems
 - Windows 2019
 - Windows 2016
 - Windows 2012 / 2012 R2
 - Windows 2008 R2
 - Windows 10
 - Windows 8 / 8.1
 - Windows 7
- PaaS Targets
 - OpenShift 3.3+
 - Kubernetes
- Orchestrator Targets
 - Action Script

For information about these targets, see the *Turbonomic Target Configuration Guide*.

12. Log in to the Turbonomic user interface and set the administrator user account password.

After the components start up, in your Web browser, type the static IP address of your Turbonomic VM. Your browser redirects to `https://[MyIPAddress]/app/index.html#/authentication/login`. This is the login page for Turbonomic users.

Turbonomic includes a default user account named `administrator`. You cannot delete this account, and you must set your own password for it.

In the login page, enter the information as required, and make a note of it.

- Use the default credential for **USERNAME**: `administrator`.
- Type a password for **PASSWORD**.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

- Type the password again to verify it for **REPEAT PASSWORD**.
- Click **CONFIGURE**.

This is the account you will use to access the Turbonomic user interface with administrator permissions. *Be sure to save the user interface administrator account credentials in a safe place.*

NOTE:

The initial login is always for the `administrator` account. This is an administration *user* account. Do not confuse this with the Turbonomic System Administrator account that you previously set up to log into shell sessions on the VM itself.

13. After you have logged in as `administrator`, you can create other user accounts, and you can give them various roles. For more information about user accounts and roles, see the *Turbonomic User Guide*.



General Configuration Tasks

After you install the Turbonomic instance, perform the following configuration tasks:

- (Required) Synchronize the system clock and configure your time servers.
- (Optional) Enforce secure access by installing a trusted certificate.

(Required) Synchronizing Time

It is important that you synchronize the clock on the Turbonomic instance with the other devices on the same network. By default, the Turbonomic server is configured to synchronize with any one of the following time servers:

- `0.centos.pool.ntp.org`
- `1.centos.pool.ntp.org`
- `2.centos.pool.ntp.org`
- `3.centos.pool.ntp.org`

To synchronize with these servers, your installation of Turbonomic must have access to the internet. If your environment restricts internet access, then you have to configure synchronization with a time server on your network.

In all cases, you should verify that the Turbonomic clock is properly synchronized. To check the system clock:

1. Open an SSH terminal session to your Turbonomic instance.

Log in with the System Administrator that you set up when you installed Turbonomic:

- Username: `turbo`
- Username: `[your_private_password]`

2. Verify your time settings.

Execute the `date` command. You should see results similar to:

```
Thu Feb 2 14:25:45 UTC 2019
```

To verify the time, compare the `date` output with the output from a known UTC time server.

Alternately you can execute the command, `timedatectl`. The output should be similar to:

```
Local time: Fri 2019-12-06 21:09:26 UTC
Universal time: Fri 2019-12-06 21:09:26 UTC
RTC time: Fri 2019-12-06 21:09:27
Time zone: UTC (UTC, +0000)
NTP enabled: yes
NTP synchronized: yes
RTC in local TZ: no
DST active: n/a
```

This tells you whether you have NTP enabled, and whether it is currently synchronized, along with other time synchronization information.

If the output is correct *and* your environment has access to the internet, you can assume the system clock is synchronized.

If the output is incorrect, or if you need to configure synchronization with a time server on your network, you must configure `chrony` on the server instance.

To set up `chrony` on your Turbonomic instance:

1. Open an SSH terminal session to your Turbonomic instance.
2. Open the `chrony` configuration file.

For example, execute the command: `sudo vi /etc/chrony.conf`

3. Specify the time servers that you want to use in your environment.

The `chrony` file includes the following statements to configure time servers:

```
server 0.centos.pool.ntp.org iburst
server 1.centos.pool.ntp.org iburst
server 2.centos.pool.ntp.org iburst
server 3.centos.pool.ntp.org iburst
```

Enter statements for the servers you want to use. Then delete or comment out the statements that you do not want to use.

Specify a time server via the following command syntax:

```
server My_Time_Server_Name iburst
```

4. Save the file.
5. Restart the `chrony` service.

Execute the command: `sudo systemctl restart chronyd`

6. Verify that your time is correct.

Execute the `date` command. You should see results similar to:

```
Thu Feb 2 14:25:45 UTC 2019
```

To verify the time, compare the `date` output with the output from a known UTC time server.

If the output is correct you can assume the system clock is synchronized.

If the output is incorrect, contact your support representative.

(Optional) Enforcing Secure Access

If your company policy requires secure access, you can use a certificate with you LDAP service to set up secure access for your users. For example, you can configure Active Directory (AD) accounts to manage *External Authentication* for users or user groups. The user interface to enable AD includes a **Secure** option, which enforces certificate-based security. For more information, see "Managing User Accounts" in the *Turbonomic User Guide*.

If your LDAP service uses a Certificate Authority (CA), then the certificate signed by that CA should support this feature as it is. Simply turn on the **Secure** option when you are setting up your AD connection.

If your LDAP service uses a self-signed certificate, then you must install that certificate on the Turbonomic authorization pod. The steps you will perform include:

- Get the certificate from your LDAP server
- Import the certificate to the platform's TrustStore
- Add the certificate to the Turbonomic platform's authorization pod
- Enable the TrustStore in the Turbonomic platform's Operator chart

This section describes how to set up secure access from an LDAP server. It assumes you have authorization to get a certificate from the LDAP server, as well as admin authority on the Turbonomic platform.

To set up secure access:

1. Open an SSH terminal session to your Turbonomic instance.

Log in with the System Administrator that you set up when you installed Turbonomic:

- Username: `turbo`
- Password: `[your_private_password]`

2. Download your LDAP Server certificate to the Turbonomic instance.

Acquire a certificate from your LDAP administrator, and download it to the Turbonomic platform. For example, you can download it to the file `/tmp/ldapserverserver.pem`:

3. Import the `.pem` file to the Turbonomic TrustStore.

This step modifies the `cacerts` file on the Turbonomic platform.

NOTE:

To import a certificate to the Turbonomic TrustStore, you must use the `keytool` utility. To install this utility, execute the command:

```
sudo yum install java-1.8.0-openjdk
```

This installs the utility in `/usr/bin/keytool`.

If an alias for an LDAP certificate already exists, delete that certificate. For example, assuming the alias `ldapcert1`, execute the following command:


```
keytool -delete -alias ldapcert1 -keystore cacerts -storepass changeit
```

Then use the following command to import your new certificate to the TrustStore:

```
keytool -import -alias ldapcert1 -file /tmp/ldapserver.pem -keystore cacerts
-storepass changeit -noprompt
```

4. Add the TrustStore to the Turbonomic authorization pod.

Execute the following command to copy the `cacerts` file into the authorization pod:

```
kubectl cp cacerts $auth_pod:/home/turbonomic/data/cacerts
```

5. Update the platform's Operator Chart to use the TrustStore.

- a. Open the chart file for editing.

Open the file, `/opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_xl_cr.yaml`.

- b. Add the TrustStore as an authorization spec for the component options.

In the chart file, find the `spec:` section. Within that section, find the `auth:` subsection.

This should be the second subsection in `spec:`, after `global:`. If there is no `auth:` subsection, you can add it to `spec:`.

- c. Add the TrustStore to the `auth:` subsection.

You will add the TrustStore path to a `javaComponentOptions:` statement within the `auth:` subsection. Add the path as a `-D` option. Use the same path that you copied the `cacerts` file to in the Turbonomic authorization pod. In the above example, you copied it to `$auth_pod:/home/turbonomic/data/cacerts`.

Following the above example, the `auth:` subsection should be similar to the following:

```
# Pass in the JAVA_OPTS to the auth POD to set up additional options such as
# a trustStore for AD Certificate(s) for LDAPS (Secure LDAP)
auth:
  javaComponentOptions: "-Djavax.net.ssl.trustStore=/home/turbonomic/data/cacerts"
```

- d. Save the `charts_v1alpha1_xl_cr.yaml` file.

6. Apply your Operator Chart changes to the Turbonomic platform.

Execute the following command:

```
kubectl apply -f
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_xl_cr.yaml
```

This restarts the authorization component so it can use the new setting. As the component restarts, the `rsyslog` output should include the following Message:

```
-Djavax.net.ssl.trustStore=/home/turbonomic/data/cacerts
```



License Installation and First-time Login

Before you begin, make sure you have your full or trial license key file that was sent to you in a separate email. Save the license file on your local machine so you can upload it to your Turbonomic installation.

To use Turbonomic for the first time, perform the following steps:

1. Type the IP address of your installed Turbonomic instance in a Web browser to connect to it.
2. Log in to Turbonomic.
 - Use the default credential for **USERNAME**: administrator.
 - Type a password for **PASSWORD**.
 - Type the password again to verify it for **REPEAT PASSWORD**.
 - Click **CONFIGURE**.
3. Continue setting up your Turbonomic installation.

Click **LET'S GO**.
4. Open the **Enter License** fly-out.

Click **IMPORT LICENSE**.
5. Upload your license key file.
 - a. In the Enter License fly-out, you can upload the license in one of the following ways:
 - Drag the license key file into the Enter License fly-out.
 - Browse to the license key file.Be sure to upload only .xml or .lic files.
 - b. Click **SAVE**.

Depending on which license you have installed, the license enables either a trial or a full unlimited license for Turbonomic.



Single Sign-On Authentication

If your company policy supports Single Sign-On (SSO) authentication, Turbonomic enables SSO authentication by using Security Assertion Markup Language (SAML) 2.0.

At a high-level, the process involves:

- Creating external groups or at least one external user for SSO. See "Managing User Accounts" in the *Turbonomic User Guide*.
- Configuring Turbonomic to connect to the SAML Identity Provider (IdP). See [Configuring Single Sign-On \(on page 20\)](#).

When SSO is enabled, use your SSO credentials to log in to your Turbonomic instance. Do not use your local or Active Directory (AD) credentials for the login. The Identity Provider (IdP) will perform the authentication.

Prerequisites

Before you begin, make sure the IdP is set up for SSO. You can use a proprietary or public IdP. For examples of settings for a public Okta IdP, see [What Are the Typical Settings for an IdP? \(on page 31\)](#).

Configuring Single Sign-On

To configure Single Sign-On, perform these steps:

1. (Required) Create external groups or at least one external user for SSO.

IMPORTANT:

When SSO is enabled, Turbonomic only permits logins via the SSO IdP. Whenever you navigate to your Turbonomic installation, it redirects you to the SSO Identity Provider (IdP) for authentication before displaying the Turbonomic user interface.

Before you enable SSO for your Turbonomic installation, *you must configure at least one SSO user with Turbonomic administrator privileges*. If you do not, then once you enable SSO you will not be able to configure any SSO users in Turbonomic. To authorize an SSO user as an administrator, use **EXTERNAL AUTHENTICATION** to do one of the following:

- Configure a single SSO user with administrator authorization.
Add an external user. The username must match an account that is managed by the IdP.
- Configure an SSO user group with administrator authorization.
Add an external group. The group name must match a user group on the IdP, and that group must have at least one member.

For information about creating external groups or external users for SSO, see "Managing User Accounts" in the *Turbonomic User Guide*.

2. Obtain a JSESSIONID cookie and make a record of it.

To obtain a JSESSIONID cookie, use this curl command:

```
curl -k -v 'https://<IP_Address>/vmturbo/rest/login' --data
'username=administrator&password=<my_password>'
```

where <IP_Address> is the IP address or host name of your Turbonomic instance and <my_password> is the password for your Turbonomic administrator user account.

For example: `curl -k -v 'https://10.10.10.123/vmturbo/rest/login' --data 'username=administrator&password=welcome57!'`

3. (Required) Ensure that chrony is configured and the system time on your Turbonomic instance is correct.

For instructions, see [Synchronizing Time \(on page 14\)](#).

4. Obtain the metadata from your IdP.

- a. Contact your security administrator to obtain the metadata from IdP.
- b. Save the metadata file in a directory on your local machine.
- c. Compare your metadata to the sample provided in [Example of IdP Metadata \(on page 22\)](#).

If your metadata includes optional attribute tags that are not listed in the example, remove those optional attribute tags since they are not supported.

- d. (Required) Name the metadata file: `metadata.xml`
5. Navigate to the local directory where you saved the metadata.xml file.
 6. Upload the IdP metadata to import it.

Run this curl command from the local directory where you saved the metadata.xml file:

```
curl -v -k --cookie 'JSESSIONID=<jsessionid_value>' -X POST -F file=@metadata.xml
https://<IP_Address>/vmturbo/rest/saml/idpmetadata
```

where <jsessionid_value> is the JSESSION cookie that you previously obtained and <IP_Address> is the IP address or host name of your Turbonomic instance.

For example: `curl -v -k --cookie 'JSESSIONID=node0p61kwex749dcw5ipbne4rm970.node0' -X POST -F file=@metadata.xml https://10.10.10.123/vmturbo/rest/saml/idpmetadata`

7. Obtain a key store to support IdP.

Generate a key store for SAML that supports IdP by using a security utility like Java SDK keytool.

NOTE:

During the process to generate a key store, you also create an alias. For the alias password, enter the same password that you used for the key store.

8. Save the key store file in the same local directory where you saved the metadata.xml file.

9. Obtain a certificate from IdP.

Contact your security administrator to obtain a certificate from IdP.

10. Import the IdP certificate into the key store.

11. Install the key store.

Run the curl command from the local directory where you saved the key store file:

```
curl -v -k --cookie 'JSESSIONID=<jsessionid_value>' -X POST -F
file=@<keystore_file_for_saml> https://<IP_Address>/vmturbo/rest/saml/keystore
```

where <jsessionid_value> is the JSESSION cookie that you obtained, <keystore_file_for_saml> is your key store file for SAML, and <IP_Address> is the IP address or host name of your Turbonomic instance.

For example: `curl -v -k --cookie 'JSESSIONID=node0p61kwex749dcw5ipbne4rm970.node0' -X POST -F file=@samlKeystore.jks https://10.10.10.123/vmturbo/rest/saml/keystore`

12. Update the SAML configuration.

Use curl to update the values for the SAML configuration:

```
curl -k 'https://<IP_Address>/vmturbo/rest/saml' -H 'cookie:
JSESSIONID=<jsessionid_value>' -H 'content-type: application/json' --data-binary
'{"entityId": "<IdP_Audience_Restriction>", "enabled": true, "externalIP": "<IP_Address>",
"password": "<keystore_password>", "alias": "<priv_key_alias>"}
```

where <IP_Address> is the IP address or host name of your Turbonomic instance. For the --data-binary parameters, specify the following values:

- entityId: The IdP's Audience Restriction property
- enabled: Type true to enable SAML.
- externalIP: The host name or IP address of your Turbonomic instance
- password: The key store password
- alias: The alias for the private key

For example:

```
curl -k 'https://10.10.10.123/vmturbo/rest/saml' -H 'cookie:
JSESSIONID=node0p61kwex749dcw5ipbne4rm970.node0' -H 'content-type: application/
json' --data-binary '{"entityId": "turbo", "enabled": true, "externalIP": "10.10.10.123",
"password": "nalle123", "alias": "apollo}"'
```

13. Restart the API component.

- Open an SSH terminal session to your Turbonomic instance.


```

        p/qaHYcQd6i2vyor888DLHDPXhSKWhpG
    </ds:X509Certificate>
</ds:X509Data>
</ds:KeyInfo>
</md:KeyDescriptor>
<md:NameIDFormat>urn:oasis:names:tc:SAML:1.1:nameid-format:unspecified</md:Name
eIDFormat>
    <md:NameIDFormat>urn:oasis:names:tc:SAML:1.1:nameid-format:emailAddress</md:Name
ameIDFormat>
    <md:SingleSignOnService Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POS
T"
        Location="https://dev-771202.oktapreview.com/app/ibmdev771202_turbo2_1/exkex
l6xc9MhzqiC30h7/sso/saml"/>
    <md:SingleSignOnService Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Red
irect"
        Location="https://dev-771202.oktapreview.com/app/ibmdev771202_turbo2_1/exkex
l6xc9MhzqiC30h7/sso/saml"/>
    </md:IDPSSODescriptor>
</md:EntityDescriptor>
    
```

Disabling Single Sign-On

If for some reason you no longer want to use SSO, you can disable it for your Turbonomic installation. To disable Single Sign-On, perform these steps:

1. Update the SAML configuration to disable it.

Use curl to update the values for the SAML configuration:

```

curl -k 'https://<IP_Address>/vmturbo/rest/saml' -H 'cookie:
JSESSIONID=<jsessionid_value>' -H 'content-type: application/json' --data-binary
'{"entityId": "<IdP_Audience_Restriction>", "enabled": false, "externalIP": "<IP_Address>",
"password": "<keystore_password>", "alias": "<priv_key_alias>"}'
    
```

where <IP_Address> is the IP address or host name of your Turbonomic instance.

For the --data-binary parameters, specify the following values:

- entityId: The IdP's Audience Restriction property
- enabled: Type false to disable SAML.
- externalIP: The host name or IP address of your Turbonomic instance
- password: The key store password
- alias: The alias for the private key

For example:

```

curl -k 'https://10.10.10.123/vmturbo/rest/saml' -H 'cookie:
JSESSIONID=node0p6lkwex749dcw5ipbne4rm970.node0' -H 'content-type: application/json'
--data-binary '{"entityId": "turbo", "enabled": false, "externalIP": "10.10.10.123",
"password": "nalle123", "alias": "apollo"}'
    
```

2. Restart the API component.
 - a. Open an SSH terminal session to your Turbonomic instance.
 - b. Use sudo as root.

```
sudo bash
```
 - c. Restart your API component.

```
turboctl restart api
```
3. Verify that the configuration is successful.
 - a. Navigate to the Turbonomic User Interface.

You will no longer be redirected to your IdP for authentication. You will be redirected to the default Turbonomic login screen.
 - b. Log in with a local account or an Active Directory (AD) account.

Support for Single Logout

If you are using the SSO feature, Turbonomic supports the Single Logout feature provided by Security Assertion Markup Language (SAML) 2.0. When you click **Logout** in the Turbonomic session that has SSO enabled, the SAML 2.0 Single Logout feature terminates the Turbonomic session, the browser session, the Identity Provider (IdP) session, and sessions at other Service Providers (SP) connected to the same IdP session.

If you want to use this feature, contact your security administrator to configure it.

The following are requirements:

- The `Single Logout` setting must be enabled on the IdP.
- The IdP needs to trust the Turbonomic SAML key store certificate.

If the IdP does not enable or support Single Logout, you need to manually log out from the IdP to fully log out from Turbonomic.

If you close the browser without clicking **Logout** or if your browser session times out, you can log in again provided the Turbonomic or the IdP session is valid.



Updating Turbonomic to a New Version

Turbonomic continually and rapidly innovates and improves all aspects of this product. This means that Turbonomic periodically releases newer versions of this product. You should check regularly to see if a new version is available.

When a new version is available, it is important to properly update your existing installed instance, rather than just install a new one. When you first installed Turbonomic, you put into place sophisticated data collection and analysis processes. Internal to the installation is an integrated database that retains performance data from across your virtual environment. Turbonomic uses this historical data for right-sizing, projecting trends, and other analysis. This means that the database is important to Turbonomic *and becomes more so over time*. Properly updating your installation of Turbonomic preserves the database for continued use.

Before you begin the update procedure:

- Make sure you have the email that Turbonomic sent to you with links to the Turbonomic .OVA file and to the ISO image.
- Ensure that the physical machine hosting the VM meets the minimum requirements (see [Minimum Requirements \(on page 5\)](#)).

You can update your Turbonomic VM using the offline method or the online method if you have access to the Internet.

Offline Update

To perform an offline update of your Turbonomic installation:

1. Save a snapshot of your current Turbonomic VM.

Before updating, you should properly shut down (not power off) the Turbonomic VM. To do so, type:

```
sudo init 0
```

Then, perform a snapshot (or clone the VM). This provides a reliable restore point you can turn to in the event that trouble occurs during the update. After you have the snapshot, bring the VM back online.

2. Download and attach the ISO image to the VM that runs Turbonomic.

Refer to the email you received from Turbonomic for links to the Turbonomic .OVA file and to the ISO image.

3. Mount the ISO image by logging in to vCenter.
 - a. In vCenter, navigate to the Turbonomic VM.
 - b. Right-click the VM and choose **Edit Settings**.
 - c. In the CD/DVD Drive drop-down menu:
 - i. Choose **Datastore ISO**.
 - ii. Browse to the Turbonomic update ISO image and choose it.
 - d. Ensure that the **Connect at power on** checkbox is selected.
4. Log in to the Turbonomic VM.
Use SSH to log in to the Turbonomic VM using the turbo account and password.
5. Make the directory and mount the ISO image.

Type:

```
sudo su -
mkdir /mnt/iso
mount /dev/cdrom /mnt/iso
```

6. Verify the correct version of the ISO image is mounted.

Type: `ls /mnt/iso`

Verify that the ISO image contains the correct version for your update.

7. Load the latest Docker images.

Type: `/mnt/iso/turboload.sh`

8. Execute these commands to update Turbonomic.

```
exit
/mnt/iso/turboupgrade.sh | tee /opt/turbonomic/t8c_upgrade_$(date +%Y-%m-%d_%H_%M_%S).log
```

Wait until the script is finished. You should see the message:

```
XL upgrade finished successfully
```

9. Clear your browser data and refresh your browser.

After clearing the browser data and refreshing your browser, you have full access to Turbonomic features.

However, features that rely on current analysis data will not be available until after a full market cycle — usually 10 minutes. For example, the Pending Actions charts will not show any actions until after a full market cycle.

10. Notify other users to clear their browser data and refresh their Turbonomic browser sessions.

Online Update

This method assumes that you have direct access to the Internet or access to the Internet through a proxy server.

NOTE:

If you are installing from behind a firewall, make sure you can access `https://hub.docker.com` through port 443.

To perform an online update of your Turbonomic installation:

1. Save a snapshot of your current Turbonomic VM.

Before updating, you should properly shut down (not power off) the Turbonomic VM. To do so, type:

```
sudo init 0
```

Then, perform a snapshot (or clone the VM). This provides a reliable restore point you can turn to in the event that trouble occurs during the update. After you have the snapshot, bring the VM back online.

2. If you are upgrading from an earlier release family, update the `operator` yml file.

You identify release families by the first two point tokens in the version number. For example, 7.17.9 and 7.21.0 are from different release families; 7.17 and 7.21, respectively.

For a new release family, the product uses an updated `operator` utility. In that case, you must update the `operator` file.

To update the file, execute the following commands in your shell session:

- `cd /opt/turbonomic/kubernetes/operator/deploy/`
- `curl -O https://raw.githubusercontent.com/turbonomic/t8c-install/7.21/operator/deploy/operator.yml`
- `kubectl apply -f operator.yml`

3. Update the version in your `charts_v1alpha1_xl_cr.yml` file.

Open `charts_v1alpha1_xl_cr.yml` for editing. For example:

```
vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_xl_cr.yml
```

Then edit the file to specify which Turbonomic version that you are installing. In the `global` section, edit the value for the `tag` parameter. For example, for an update to 7.21.0, the changed entry would appear as follows:

```
global:
# registry: index.docker.io
# imageUsername: turbouser
# imagePassword: turbopassword
repository: turbonomic
tag: 7.21.0
```

After you make your change, save the file.

4. Start the online update.

Execute the `kubectl apply` command:

```
kubectl apply -f
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_xl_cr.yml
```

This command downloads the newer Docker images from the Docker Hub and then upgrades the components.

Wait until the update is finished. You should see the message:

```
XL upgrade finished successfully
```

5. Clear your browser data and refresh your browser.

After clearing the browser data and refreshing your browser, you have full access to Turbonomic features.

However, features that rely on current analysis data will not be available until after a full market cycle — usually 10 minutes. For example, the Pending Actions charts will not show any actions until after a full market cycle.

6. Notify other users to clear their browser data and refresh their Turbonomic browser sessions.



Appendix A: Turbonomic Components

The following listings show the components that Turbonomic creates as part of the installation process.

Core Components For Turbonomic

- rsyslog
- nginx
- consul
- auth
- clustermgr
- api
- market
- action-orchestrator
- topology-processor
- arangodb
- repository
- group
- history
- plan-orchestrator
- reporting

Mediation Components For Turbonomic

- mediation-actionscript
- mediation-appdynamics
- mediation-hpe3par
- mediation-hyperv
- mediation-netapp
- mediation-oneview
- mediation-pure
- mediation-ucs

- mediation-vcenter
- mediation-vcenterbrowsing
- mediation-vmax
- mediation-vmm



Appendix B: What Are the Typical Settings for an IdP?

Before you begin configuring Single Sign-On (SSO), you need to make sure the IdP is set up for SSO.

Here are typical settings for a public Okta IdP which may be useful when you set up your IdP.

SAML Settings: GENERAL	
Setting	Example
Single Sign On URL	<code>https://10.10.10.123/vmturbo/saml/SSO</code>
Recipient URL	<code>https://10.10.10.123/vmturbo/saml/SSO</code>
Destination URL	<code>https://10.10.10.123/vmturbo/saml/SSO</code>
Audience Restriction	<code>urn:test:turbo:markharm</code>
Default Relay State	
Name ID Format	Unspecified
Application username	The username for the account that is managed by Okta
Response	Signed
Assertion Signature	Signed
Signature Algorithm	RSA_SHA256
Digital Algorithm	SHA256
Assertion Encryption	Unencrypted
SAML Single Logout	Enabled
Single Logout URL	<code>https://10.10.10.123/vmturbo/rest/logout</code>
SP Issuer	turbo

SAML Settings: GENERAL

Setting	Example
Signature Certificate	Example.cer (CN=apollo)
authnContextClassRef	PasswordProtectedTransport
Honor Force Authentication	Yes
SAML Issuer ID	http://www.okta.com/\$(org.externalKey)

SAML Settings: GROUP ATTRIBUTE STATEMENTS

Name	Name Format	Filter
group	Unspecified	Matches regex:.*admin.*.